

Lecture 11

structure with regular union	structure with anonymous union
<pre>struct { char title[50]; char author[50]; union { float dollars; int yens; } price; } book;</pre>	<pre>struct { char title[50]; char author[50]; union { float dollars; int yens; }; } book;</pre>

The only difference between the two pieces of code is that in the first one we have given a name to the union (`price`) and in the second one we have not. The difference is seen when we access the members `dollars` and `yens` of an object of this type. For an object of the first type, it would be:

```
book.price.dollars
book.price.yens
```

whereas for an object of the second type, it would be:

```
book.dollars
book.yens
```

Once again I remind you that because it is a union and not a struct, the members `dollars` and `yens` occupy the same physical space in the memory so they cannot be used to store two different values simultaneously. You can set a value for `price` in dollars or in yens, but not in both.

Enumerations (enum)

Enumerations create new data types to contain something different that is not limited to the values fundamental data types may take. Its form is the following:

```
enum enumeration_name {
  value1,
  value2,
  value3,
  .
} object_names;
```

For example, we could create a new type of variable called `color` to store colors with the following declaration:

```
enum colors_t {black, blue, green, cyan, red, purple, yellow, white};
```

Notice that we do not include any fundamental data type in the declaration. To say it somehow, we have created a whole new data type from scratch without basing it on any other existing type. The possible values that variables of this new type `color_t` may take are the new constant values included within braces. For example, once the `colors_t` enumeration is declared the following expressions will be valid:

```
colors_t mycolor;
mycolor = blue;
if (mycolor == green) mycolor = red;
```

Enumerations are type compatible with numeric variables, so their constants are always assigned an integer numerical value internally. If it is not specified, the integer value equivalent to the first possible value is equivalent to 0 and the following ones follow a +1 progression. Thus, in our data type `colors_t` that we have defined above, `black` would be equivalent to 0, `blue` would be equivalent to 1, `green` to 2, and so on.

We can explicitly specify an integer value for any of the constant values that our enumerated type can take. If the constant value that follows it is not given an integer value, it is automatically assumed the same value as the previous one plus one. For example:

```
enum months_t { january=1, february, march, april,  
               may, june, july, august,  
               september, october, november, december} y2k;
```

In this case, variable `y2k` of enumerated type `months_t` can contain any of the 12 possible values that go from `january` to `december` and that are equivalent to values between 1 and 12 (not between 0 and 11, since we have made `january` equal to 1).

Object Oriented Programming

Classes (I)

A *class* is an expanded concept of a data structure: instead of holding only data, it can hold both data and functions.

An *object* is an instantiation of a class. In terms of variables, a class would be the type, and an object would be the variable.

Classes are generally declared using the keyword `class`, with the following format:

```
class class_name {
    access_specifier_1:
        member1;
    access_specifier_2:
        member2;
} object_names;
```

Where `class_name` is a valid identifier for the class, `object_names` is an optional list of names for objects of this class. The body of the declaration can contain members, that can be either data or function declarations, and optionally access specifiers.

All is very similar to the declaration on data structures, except that we can now include also functions and members, but also this new thing called *access specifier*. An access specifier is one of the following three keywords: `private`, `public` or `protected`. These specifiers modify the access rights that the members following them acquire:

- `private` members of a class are accessible only from within other members of the same class or from their *friends*.
- `protected` members are accessible from members of their same class and from their friends, but also from members of their derived classes.
- Finally, `public` members are accessible from anywhere where the object is visible.

By default, all members of a class declared with the `class` keyword have private access for all its members. Therefore, any member that is declared before one other class specifier automatically has private access. For example:

```
class CRectangle {
    int x, y;
    public:
        void set_values (int,int);
        int area (void);
} rect;
```

Declares a class (i.e., a type) called `CRectangle` and an object (i.e., a variable) of this class called `rect`. This class contains four members: two data members of type `int` (member `x` and member `y`) with private access (because private is the default access level) and two member functions with public access: `set_values()` and `area()`, of which for now we have only included their declaration, not their definition.

Notice the difference between the class name and the object name: In the previous example, `CRectangle` was the class name (i.e., the type), whereas `rect` was an object of type `CRectangle`. It is the same relationship `int` and `have` in the following declaration:

```
int a;
```

where `int` is the type name (the class) and `a` is the variable name (the object).

After the previous declarations of `CRectangle` and `rect`, we can refer within the body of the program to any of the public members of the object `rect` as if they were normal functions or normal variables, just by putting the object's name followed by a dot (`.`) and then the name of the member. All very similar to what we did with plain data structures before. For example:

```
rect.set_values (3,4);  
myarea = rect.area();
```

The only members of `rect` that we cannot access from the body of our program outside the class are `x` and `y`, since they have private access and they can only be referred from within other members of that same class.

Here is the complete example of class `CRectangle`:

```
// classes example  
#include <iostream>  
using namespace std;  
  
class CRectangle {  
    int x, y;  
public:  
    void set_values (int,int);  
    int area () {return (x*y);}  
};  
  
void CRectangle::set_values (int a, int b) {  
    x = a;  
    y = b;  
}  
  
int main () {  
    CRectangle rect;  
    rect.set_values (3,4);  
    cout << "area: " << rect.area();  
    return 0;  
}
```

area: 12

The most important new thing in this code is the operator of scope (`::`, two colons) included in the definition of `set_values()`. It is used to define a member of a class from outside the class definition itself.

You may notice that the definition of the member function `area()` has been included directly within the definition of the `CRectangle` class given its extreme simplicity, whereas `set_values()` has only its prototype declared within the class, but its definition is outside it. In this outside declaration, we must use the operator of scope (`::`) to specify that we are defining a function that is a member of the class `CRectangle` and not a regular global function.

The scope operator (`::`) specifies the class to which the member being declared belongs, granting exactly the same scope properties as if this function definition was directly included within the class definition. For example, in the function `set_values()` of the previous code, we have been able to use the variables `x` and `y`, which are private members of class `CRectangle`, which means they are only accessible from other members of their class.

The only difference between defining a class member function completely within its class or to include only the prototype and later its definition, is that in the first case the function will automatically be considered an inline member function by the compiler, while in the second it will be a normal (not-inline) class member function, which in fact supposes no difference in behavior.

Members `x` and `y` have private access (remember that if nothing else is said, all members of a class defined with keyword `class` have private access). By declaring them private we deny access to them from anywhere outside the

class. This makes sense, since we have already defined a member function to set values for those members within the object: the member function `set_values()`. Therefore, the rest of the program does not need to have direct access to them. Perhaps in a so simple example as this, it is difficult to see an utility in protecting those two variables, but in greater projects it may be very important that values cannot be modified in an unexpected way (unexpected from the point of view of the object).

One of the greater advantages of a class is that, as any other type, we can declare several objects of it. For example, following with the previous example of class `CRectangle`, we could have declared the object `rectb` in addition to the object `rect`:

<pre>// example: one class, two objects #include <iostream> using namespace std; class CRectangle { int x, y; public: void set_values (int,int); int area () {return (x*y);} }; void CRectangle::set_values (int a, int b) { x = a; y = b; } int main () { CRectangle rect, rectb; rect.set_values (3,4); rectb.set_values (5,6); cout << "rect area: " << rect.area() << endl; cout << "rectb area: " << rectb.area() << endl; return 0; }</pre>	<pre>rect area: 12 rectb area: 30</pre>
--	---

In this concrete case, the class (type of the objects) to which we are talking about is `CRectangle`, of which there are two instances or objects: `rect` and `rectb`. Each one of them has its own member variables and member functions.

Notice that the call to `rect.area()` does not give the same result as the call to `rectb.area()`. This is because each object of class `CRectangle` has its own variables `x` and `y`, as they, in some way, have also their own function members `set_value()` and `area()` that each uses its object's own variables to operate.

That is the basic concept of *object-oriented programming*: Data and functions are both members of the object. We no longer use sets of global variables that we pass from one function to another as parameters, but instead we handle objects that have their own data and functions embedded as members. Notice that we have not had to give any parameters in any of the calls to `rect.area` or `rectb.area`. Those member functions directly used the data members of their respective objects `rect` and `rectb`.

Constructors and destructors

Objects generally need to initialize variables or assign dynamic memory during their process of creation to become operative and to avoid returning unexpected values during their execution. For example, what would happen if in the previous example we called the member function `area()` before having called function `set_values()`? Probably we would have gotten an undetermined result since the members `x` and `y` would have never been assigned a value.

In order to avoid that, a class can include a special function called `constructor`, which is automatically called whenever a new object of this class is created. This constructor function must have the same name as the class, and cannot have any return type; not even `void`.

We are going to implement `CRectangle` including a constructor:

```
// example: class constructor
#include <iostream>
using namespace std;

class CRectangle {
    int width, height;
public:
    CRectangle (int,int);
    int area () {return (width*height);}
};

CRectangle::CRectangle (int a, int b) {
    width = a;
    height = b;
}

int main () {
    CRectangle rect (3,4);
    CRectangle rectb (5,6);
    cout << "rect area: " << rect.area() << endl;
    cout << "rectb area: " << rectb.area() << endl;
    return 0;
}
```

```
rect area: 12
rectb area: 30
```

As you can see, the result of this example is identical to the previous one. But now we have removed the member function `set_values()`, and have included instead a constructor that performs a similar action: it initializes the values of `x` and `y` with the parameters that are passed to it.

Notice how these arguments are passed to the constructor at the moment at which the objects of this class are created:

```
CRectangle rect (3,4);
CRectangle rectb (5,6);
```

Constructors cannot be called explicitly as if they were regular member functions. They are only executed when a new object of that class is created.

You can also see how neither the constructor prototype declaration (within the class) nor the latter constructor definition include a return value; not even `void`.

The *destructor* fulfills the opposite functionality. It is automatically called when an object is destroyed, either because its scope of existence has finished (for example, if it was defined as a local object within a function and the function ends) or because it is an object dynamically assigned and it is released using the operator `delete`.

The destructor must have the same name as the class, but preceded with a tilde sign (`~`) and it must also return no value.

The use of destructors is especially suitable when an object assigns dynamic memory during its lifetime and at the moment of being destroyed we want to release the memory that the object was allocated.

Lecture 11

```
// example on constructors and destructors
#include <iostream>
using namespace std;

class CRectangle {
    int *width, *height;
public:
    CRectangle (int,int);
    ~CRectangle ();
    int area () {return (*width * *height);}
};

CRectangle::CRectangle (int a, int b) {
    width = new int;
    height = new int;
    *width = a;
    *height = b;
}

CRectangle::~~CRectangle () {
    delete width;
    delete height;
}

int main () {
    CRectangle rect (3,4), rectb (5,6);
    cout << "rect area: " << rect.area() << endl;
    cout << "rectb area: " << rectb.area() << endl;
    return 0;
}
```

```
rect area: 12
rectb area: 30
```

Overloading Constructors

Like any other function, a constructor can also be overloaded with more than one function that have the same name but different types or number of parameters. Remember that for overloaded functions the compiler will call the one whose parameters match the arguments used in the function call. In the case of constructors, which are automatically called when an object is created, the one executed is the one that matches the arguments passed on the object declaration:

Lecture 11

```
// overloading class constructors
#include <iostream>
using namespace std;

class CRectangle {
    int width, height;
public:
    CRectangle ();
    CRectangle (int,int);
    int area (void) {return (width*height);}
};

CRectangle::CRectangle () {
    width = 5;
    height = 5;
}

CRectangle::CRectangle (int a, int b) {
    width = a;
    height = b;
}

int main () {
    CRectangle rect (3,4);
    CRectangle rectb;
    cout << "rect area: " << rect.area() << endl;
    cout << "rectb area: " << rectb.area() << endl;
    return 0;
}
```

```
rect area: 12
rectb area: 25
```

In this case, `rectb` was declared without any arguments, so it has been initialized with the constructor that has no parameters, which initializes both `width` and `height` with a value of 5.

Important: Notice how if we declare a new object and we want to use its default constructor (the one without parameters), we do not include parentheses `()`:

```
CRectangle rectb; // right
CRectangle rectb(); // wrong!
```

Default constructor

If you do not declare any constructors in a class definition, the compiler assumes the class to have a default constructor with no arguments. Therefore, after declaring a class like this one:

```
class CExample {
public:
    int a,b,c;
    void multiply (int n, int m) { a=n; b=m; c=a*b; };
};
```

The compiler assumes that `CExample` has a default constructor, so you can declare objects of this class by simply declaring them without any arguments:

```
CExample ex;
```

But as soon as you declare your own constructor for a class, the compiler no longer provides an implicit default constructor. So you have to declare all objects of that class according to the constructor prototypes you defined for the class: